

Bitnami Joomla!

How-To Guides

- 1. How to start/stop the servers?
 - 1.1. Graphical tool
 - 1.2. Command line tool
- 2. How to change the default URL to root?
 - 2.1. Automatic Approach
 - 2.2. Manual Approach
- 3. How to create a full backup of Ioomla!?
- 4. How to upgrade Joomla!?
 - 4.1. <u>Upgrading Joomla! from the</u> application
- 5. How to install a plugin on Joomla!?
- 6. How to configure the email settings of Joomla!?
- 7. How to translate Joomla! to my language?
- 8. How to enable cache settings of Ioomla!?
- 9. How to enable Gzip Page Compressor of Joomla!?
- 10. How to enable SSL?
- 11. How to debug Joomla! errors?
- the uploaded files?
- 13. Where is the administration interface of Joomla?

How to install multiple Joomla! in the same instance

- 1. Apache Configuration
- 2. MySOL Configuration
- 3. Installing new Joomla! site

How to upgrade your Joomla! instance

- 1. How can I create a backup of my instance?
- 2. How do I migrate the data to a new Bitnami Joomla! instance?
 - 2.1. Backing up the files
 - 2.2. Copying the files to the new instance
 - 2.3. Restoring files in the new instance
- 3. How to associate the previous IP address to a new instance?

Migration from local installation to the cloud

- 1. How to create our local Joomla! database backup with phpMyAdmin
- 12. How to increase the allowed size of |2. How to sync Joomla! files from the local machine to the remote machine
 - 3. How to export the Joomla! database
 - to the remote machine with phpMvAdmin

Joomla! is an open source Content Management System with a growing and active community. Joomla! creates multiple format sites from simple websites to complex corporate applications and allows

users to manage each aspect of their website through a simple, browser-based interface. Once Joomla! is up and running, users with basic word processing skills can add or edit content, update images, and to manage the critical data. Joomla! also allows developers to create and include add-ons to further customize their site.

Please, take a look to the <u>Quick Start Guide</u> to know the basic use of this Stack.

How to start/stop the servers?

Graphical tool

The native installers include a graphical tool to manage the servers easily. You can find the "manager-windows.exe", "manager-osx" or "manager-linux" tool in your **installation directory**. Using this tool, you can Start, Stop or Restart the servers and check the log files. You can click on the icon to start it.

manager-servers.png

managerosx.png On Windows: You can also start the Manager tool from shortcuts: Start -> Program Files -> Bitnami Stack -> Manager tool

Command line tool

If you prefer, you can use the "ctlscript.sh" utility from the command line. This script is in the installation directory.

linux platform.png

On Virtual Machines and Cloud images:

\$ sudo /opt/bitnami/ctlscript.sh start

A native installer on Linux:

```
$ cd ~/application-version
$ ./ctlscript.sh start
```

mac platform.png

On OS X: You can start the Manager tool from the installation directory or you can use the "ctlscript.sh" utility from a Terminal.

```
host:~ user$ cd /Applications/application-version host:~ user$ ./ctlscript.sh start
```

How to change the default URL to root?

This approach describes how to configure your application to **run in the root URL directly**. Also, you will be able to **modify the URL to a NEW_DOMAIN** using the bnconfig tool. The details are described below.

Automatic Approach

This approach is based on the <u>Bitnami Configuration Tool</u> (bnconfig).

Bitnami Cloud Hosting

The best way to change your URL in BCH is to go to your application tab and modify it there. In the Bitnami Cloud Hosting console, select Servers, choose your server, Manage and go to the Applications tab. Press there the pencil next to the application which URL you want to modify and choose Use Custom Domain.

Cloud Images and Virtual Machines

Moving the application to /

If your application is running in "/joomla" you can remove the prefix from the URL executing the following command:

\$ sudo /opt/bitnami/apps/joomla/bnconfig --appurl /

(use --help to check if that option is available for your application)

Now you will be able to access to the application at http://YOUR DOMAIN/joomla.

Updating the IP or hostname

Some applications require to update the IP/domain if the machine IP/domain changes. The bnconfig tool also has an option which updates the IP automatically during boot, called machine_hostname (use --help to check if that option is available for your application). Note that this tool changes the URL to http://NEW_DOMAIN/joomla.

sudo /opt/bitnami/apps/joomla/bnconfig --machine hostname NEW_DOMAIN

If you already moved your application to the root URL you should include both options at the same time.

sudo /opt/bitnami/apps/joomla/bnconfig --appurl / --machine_hostname NEW

If you have configured your machine to use an static domain name or IP, you **should rename or remove** the "/opt/bitnami/apps/joomla/bnconfig" file.

sudo mv /opt/bitnami/apps/joomla/bnconfig /opt/bitnami/apps/joomla/bncon

Native Installer

Remember to use your actual installation directory instead of installdir.

Moving the application to /

If your application is running in "/joomla" you can remove the prefix from the URL executing the following command:

On Linux,

```
installdir/apps/joomla/bnconfig --appurl /
On Mac OS X,
installdir/apps/joomla/bnconfig.app/Contents/MacOS/installbuilder.sh --a
On Windows,
installdir/apps/joomla/bnconfig.exe --appurl /
(use --help to check if that option is available for your application)
Now you will be able to access to the application at
http://YOUR DOMAIN instead of http://YOUR DOMAIN/joomla.
```

Updating the IP or hostname

Some applications require to update the IP/domain if the machine IP/domain changes. The bnconfig tool also has an option which updates the IP, called machine_hostname (use --help to check if that option is available for your application). Note that this tool changes the URL to http://NEW_DOMAIN/joomla.

installdir/apps/joomla/bnconfig --machine_hostname NEW_DOMAIN

If you already moved your application to the root URL you should include both options at the same time.

installdir/apps/joomla/bnconfig --appurl / --machine_hostname NEW_DOMAIN

Tabs end

Manual Approach

If you want to change the default URL from http://your_domain/joomla
to http://your_domain/joomla
to http://your_domain/joomla
to http://your_domain/joomla
to http://your_domain/joomla
prefix.conf file so that it looks like the file below:

```
DocumentRoot "/installdir/apps/joomla/htdocs"
# Alias /joomla/ "/installdir/apps/joomla/htdocs/"
# Alias /joomla "/installdir/apps/joomla/htdocs"

(...)
```

Remember that you must substitute *installdir* with your actual installation directory (for native installers) or */opt/bitnami* (for cloud images and virtual machines).

Some applications also require additional changes in their configuration files or in their database.

In this case it is also necessary to modify the following lines in "installdir/apps/joomla/conf/htaccess.conf" file:

```
# RewriteBase /joomla
...
RewriteBase /
```

Finally restart the Apache server:

\$ /installdir/ctlscript.sh restart apache

How to create a full backup of Joomla!?

Because Bitnami stacks are self-contained, the simplest option for performing your backups is to copy or compress the Bitnami Stack installation directory. To do so in a safe manner, you will need to stop all servers, so this method may not be appropriate if you have people accessing the application continously.

linux_platform.pngOn Virtual Machines and Cloud Images:

```
$ cd installdir
$ ./ctlscript.sh stop
$ cp -r installdir application-backup
```

Or you can create a tarball:

```
$ tar -czvf application-backup.tar.gz installdir
Or a zip file:
$ zip -r application-backup.zip installdir/*
```

To restore this backup you only need to uncompress the backup in the same location. It is important to use the same path that was used when the stack was originally installed.

For example if you have a backup in a Red Hat machine, you can copy it to an Ubuntu Linux machine (a different distro!) in the same location. Then start the servers and that's all.

On Virtual Machines and Cloud Images:

```
$ sudo /opt/bitnami/ctlscript.sh start
```

On OS X:

```
$ cd installdir
$ ./ctlscript.sh start
```

You just need to be carefull to keep the same permissions for the files and folders. If you installed as root make sure that in the new machine you copy the files also as root. And this case, if you are also moving MySQL or PostgreSQL, you will need to create those users in the new machine (if they don't exist yet).

win_platform.pngOn Windows you should follow the same process. Stop the servers using the shortcuts and copy the whole installation directory. To restore the system, copy the directory to a different Windows machine in the same location and follow these steps from a command prompt:

```
$ cd installdir
$ serviceinstall.bat INSTALL
```

You can access your Bitnami Application at the usual URL.

If you want to create only a database backup, check the following link for MySQL /Components/MySQL#How_to_create_a_database_backup or for PostgreSQL /Components/
PostgreSQL#How_to_create_a_database_backup.3f

How to upgrade Joomla!?

It is strongly recommended that you create a backup before starting the update process. If you have important data, it is advisable that you create and try to restore a backup to ensure that everything works properly. There are two different ways to upgrade your application.

- 1. If you want to upgrade the application and all Stack components PHP, Ruby, MySQL, Apache... You can follow the steps described at How to upgrade the full Stack migrating the data?
- 2. In case you only want to upgrade the application code without modifying any other Stack components, you should follow the guide which is in the application page itself.

Upgrading Joomla! from the application

If you want to upgrade only Joomla! application, it is possible to upgrade it from the Admin panel.

IMPORTANT. Joomla! update process does not work properly from the "Joomla! Update" section. You can find more info at http://docs.joomla.org/Ftp-update-not-working If you try to update Joomla! from the "Joomla! Update" instead of the extension manager, you will find permission errors trying to copy files.

It is suggested that rather than use the updater you install the new Joomla version using the standard **extension manager** install.

• Click on the "Joomla! new version, Update now!" link:

joomla-update1.png

• Copy the URL of the new Patch Package

joomla-update2.png

• Go to "Extensions" -> "Extension Manager" and click on the "Install from URL" tab. Copy the previous link there and click on the "Install" button.

joomla-update3.png

• If you find any Database error it is possible that you should run the "Fix database". Go to Extension Manager -> Database and click in the "Fix" button.

How to install a plugin on Joomla!?

You can install any modules from the "Plugins Manager" tool in the Administrator Panel. You can upload the module directly or can specify the link to the download. Recent versions of Joomla! Virtual Machines or AMIs already configure FTP automatically, it is not necessary to modify it.

If you have installed the Stack in your machine, it is necessary to install a FTP server in your machine. These are the settings that you should use:

FTP Host: 127.0.0.1

FTP Port: 21

FTP Username: your machine user

FTP Password: (the password of your user)

How to configure the email settings of Joomla!?

If you are using the Naitve Installer or Bitnami Cloud Hosting, you can configure the email settings during the deploy. In other case, you can configure the email settings at "Global Configuration" -> "Server". You can use the "SMTP" at the mailer and configure it with your email server provider. GMail, Yahoo and others allow to send emails with your account.

For instance, using GMail:

Mailer: SMTP

From email: myaccount@gmail.com

From name: My Name

SMTP Authentication: Yes

SMTP Security: TLS

SMTP Port: 587

SMTP Username: myaccount@gmail.com SMTP Password: your account password

SMTP Host: smtp.gmail.com

How to translate Joomla! to my language?

Bitnami Joomla! has already installed English, Spanish and more translations currently. If you want to change the Joomla language you can follow these steps:

- 1. Download your language translation from http://joomlacode.org/gf/project/jtranslation1-6/frs/
- 2. Go to Extensions -> Extension Manager in the administration panel and upload the package.
- 3. Go to Extensions -> Language Manager and enable your language for the Site and for the Administration panel.

How to enable cache settings of Joomla!?

Enabling the cache will boost the overall performance of your installation. You can enable easily the caching system throught the administrator panel of Joomla!.

Click on the System and Global Configuration tabs:

• Go to System tab and check Cache Settings configuration. Change cache setting to: ON - Conservating caching:

 Now it is required to activate the Cache Plugin. Go to Extensions > Plugin Manager (Tab), search for "cache" and enable the "System - Cache" extension.

Gzip Page Compressor saves around fifty to seventy percent of the file size. This means that it takes less time to load your pages, and less

• Click on the System and Global Configuration tabs:

How to enable Gzip Page Compressor of Joomla!?

bandwidth is used over all.

	• Go to Server tab and enable Gzip Page Compression:
	 On Linux and Mac OS X You should restart php-fpm using t command line:
	./ctlscript.sh restart php-fpm
Ho	ow to enable SSL?
	u can see how to configure Apache to enable SSL connections a w to enable SSL to access through https?

How to debug Joomla! errors?

Once Apache starts, it will create two log files, the **access_log** and the **error_log** /installdir/apache2/logs directory or in /var/log/httpd if you are using Amazon Linux or Red Hat Enterprise cloud images.

In Virtual Machines, Cloud Images and Ubuntu based Bitnami Cloud Hosting images *installdir* is **/opt/bitnami**.

The access_log file is used to track client requests. When a client requests a document from the server, Apache records several parameters associated with the request in this file, such as: the IP address of the client, the document requested, the HTTP status code, and the current time.

The error_log file is used to record important events. This file includes error messages, startup messages, and any other significant events in the life cycle of the server. This is the first place to look when you run into a problem when using Apache.

If no error is found, you will see a message similar to:

```
Syntax OK
/installdir/ctlscript.sh : httpd started
```

The main MySQL log file is created at /installdir/mysql/data/mysqld.log file.

How to increase the allowed size of the uploaded files?

You can modify the following option in the php.ini file to increase the allowed size for uploads:

```
; Maximum size of POST data that PHP will accept.
post_max_size = 16M
...
; Maximum allowed size for uploaded files.
upload max filesize = 16M
```

If you have enabled PHP-FPM (enabled by default in **Cloud Images** and **VMs**) you need to restart PHP-FPM running the following command:

sudo /opt/bitnami/ctlscript.sh restart php-fpm

Note: For native installers replace /opt/bitnami with your current installation directory.

Otherwise, you need to restart the Apache server:

sudo YOUR_INSTALLATION_DIRECTORY/ctlscript.sh restart apache

Where is the administration interface of Joomla?

The admin panel is located at http://your_domain/joomla/administrator